



---

# SIEMENS OPEN LIBRARY

---

6 – PID Configuration

JUNE 11, 2019

---

## Contents

1. Purpose .....	3
2. Intended Use.....	3
3. Revision History.....	3
4. Open Library License.....	3
5. Open Library PID Compact Setup.....	5
5.1. Initial Setup .....	5
5.2. PLC .....	5
5.2.1. Creating PID Technology Object .....	5
5.3. HMI.....	15

---

## 1. Purpose

The purpose of this document is to assist with configuration of the PID Open Library Object. In order to use the features of the built in Technology Object for the PID Compact Block, the library object requires special setup. The PID Compact Block only exists on the S7-1200 and S7-1500. The Open Library Object was written to be compatible with PID\_Compact V2.2, and capabilities cannot be guaranteed for other versions of the PID Compact block.

---

## 2. Intended Use

This document is to be used by anyone utilizing the Siemens Open Library fbPID\_CompactInterface. This document is used to configure the PLC and HMI objects for the library, as the configuration of these objects is not standard with the rest of the library.

---

## 3. Revision History

Version	Date	Author	Comments
1.0	2016-05-23	DMC	Initial Release
1.1	2016-06-20	DMC	Updated screenshots for PID_Compact and the interface function block
1.2	2016-08-23	DMC	No Changes
1.3	2016-10-11	DMC	No Changes
1.4	2017-06-27	DMC	Updated with new fbPID_Compact block and HMI_PID data type.
2.0	2017-11-3	DMC	No Changes
3.0	2018-12-05	DMC	Updates to data types used by block
4.0	2019-06-11	DMC	No Changes

---

## 4. Open Library License

Copyright (c) 2019 DMC, Inc.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN

AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

## 5. Open Library PID Compact Setup

The following steps walk through the configuration of the PID Open Library Object. In order to use the features of the built-in Technology Object settings for the PID\_Compact Block, the library object requires special setup.

The benefit of using the Library Interface block are as follows:

1. It provides an easy interface for operation and changes to the PID from an HMI faceplate.
2. It utilizes the technology object, so all of the PID functions built in to portal can still be used.

### 5.1. Initial Setup

Before starting this document please make sure you have set up your project following the steps in the Basic Setup document. Each block is dependent on global constants and clock memory bits, and will not compile without correctly completing the initial setup. The following steps need to be performed:

- Enable system and clock memory bytes on the CPU.
- Retrieve the Open Library.
- Pull the Open Library PLC tags into the project.
- Setup Mode Control, or understand of how Open Library Modes function.


### 5.2. PLC

This section covers the setup required for the PLC programming. The following steps are required:


1. Create the PID Technology object
2. Create an FB and OB to call the fbPID\_Compact block.
3. Map the fbPID\_Compact block to the PID\_Compact Technology Object.

#### 5.2.1. Creating PID Technology Object


1. Start by creating a PID\_Compact technology object. Expand the Technology Objects folder and click Add new object.




2. In the new object dialog box, give your object a name and select the PID\_Compact v2.2 block.



3. Configure your PID\_Compact technology block to fit your physical system.



4. Pull fbPID\_Compact from the Open Library Types group into the Library Blocks group to use it in our project.




- In a global data block (dbWaterSystem in this example), add a structure for all of your PID related variables. The required variables are seen in the screenshot below. This structure should include your HMI control for the PID system (udtHMI\_PID).

dbWaterSystem										
	Name	Data type	Start value	Retain	Accessible f...	Writa...	Visible in ...	Setpoint	Supervision	Comment
1	Static									
2	SOL_MainWater	"udtHMI_ValveC...			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			Main Water Valve
3	VFD_WaterPump	"udtHMI_VFD_Cont...			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			Main Water Pump
4	INT_WaterPump	"udtHMI_Interlock"			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			Main Water Pump Interlock
5	AI_WaterPumpPressure	"udtHMI_AnalogIn...			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			Main Water Pump Pressure
6	MTR_ReturnWaterPump	"udtHMI_MotorCon...			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			Return Water Pump
7	ANA_SteamValve	"udtHMI_AnalogVal...			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			Water Temperature Steam Valve
8	AO_CoolingCoil	"udtHMI_AnalogOu...			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			Water Cooling Coil
9	SystemControl	"udtHMI_SystemCo...			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			Water System Control
10	WaterTemperature	Struct			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			Water Temperature Control
11	AI_WaterTemperature	"udtHMI_AnalogIn...			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			Water Temperature Analog Input
12	PID_WaterTempInterface	"udtHMI_PID"			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>			PID Interface and Control

- Similarly, add the error structure to the errors Data Block, dbErrors\_WaterSystem in this example.


dbErrors_WaterSystem										
	Name	Data type	Offset	Start value	Retain	Accessible f...	Visible in ...	Setpoint	Comment	
1	Static				<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>		
2	SOL_MainWater	"udtError_Valve"	...		<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Main Water Valve	
3	VFD_WaterPump	"udtError_VFD"	...		<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Main Water Pump	
4	ANA_SteamValve	"udtError_AnalogV..."	...		<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Analog Steam Valve	
5	PID_WaterTemperature	"udtError_PID"	...		<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Water Temperature PID	
6	InputOutOfRange	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Input value is out of the configured range	
7	InputPERInvalid	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	InputPER value is invalid	
8	ValueOscillationFa...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Fine tuning - process value oscillation could n...	
9	ProcessValueClose...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Pre-tuning - process value is too close to set p...	
10	SetPointChangedD...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	PID set point was changed during tuning	
11	PretuningDuringFi...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Pre-tuning not allowed while fine tuning is act...	
12	InvalidOutputValu...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Pre-tuning - invalid configuration of output v...	
13	InvalidFineTuning...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Fine tuning - error occurred causing invalid p...	
14	InputInvalidFormat	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Input value has an invalid number format	
15	OutputCalculation...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Output value calculation error occurred	
16	SamplingTimeError	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	PID_Compact not called within sampling time...	
17	SetPointInvalidFor...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Set point value has an invalid number format	
18	ManualInvalidFor...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Manual value has an invalid number format	
19	SubstituteOutput...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Substitute output value has an invalid numbe...	
20	DisturbanceInvalid...	Bool	...	false	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Disturbance value has an invalid number form...	

- Add a new Cyclic Interrupt OB that will call our time sensitive cyclic operations.







8. Give the cyclic interrupt OB a name and set the cycle time to something appropriate for the application. In this case, temperature does not need a fast cycle so it was set to 100ms (100,000 $\mu$ s).




9. Add a new function block that will call our PID\_Compact and will be called from the cyclic interrupt OB. It is recommended best practice to limit logic inside an OB, and the library object requires instance memory, so we will use the FB to encapsulate our cyclic operation logic.




10. Name the cyclic function block.




11. Create an instance data block to accompany the cyclic function block.





12. Name the instance data block and give it the type of your cyclic function block.



13. Inside of the cyclic interrupt OB, drag in an instance of the cyclic FB you created.




14. Assign the instance data block as a single instance.




15. Add a multiple instance static memory variable for the fbPID\_Compact block in the fbCyclicInterrupt block.

16	ANA_SteamValve	*fbValve_Analog*	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Water Temperature Steam Valve
17	AO_CoolingCoil	*fbIO_AnalogOutp...	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Water Temperature Cooling Coil
18	PID_WaterTemperature	*fbPID_Compact*	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Water Temperature PID Interface
19	AI_WaterTemperature	*fbIO_AnalogInput*	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Water Temperature Actual


16. Drag an instance of fbPID\_Compact into a network in fbCyclicInterrupt.



- When the Call options dialog appears, choose the static memory multiple instance that you just created in the block interface.




18. Fill in the interface for your fbPID\_Compact instance. Notice the reference to the PID\_Compact technology data block as well as the HMI and Errors data block structures.




### 5.3. HMI

This section walks through the required steps to add the HMI pop-ups for the PID Interface Block.


1. Create a new Pop-up screen for the PID Faceplate.
2. Pull the fpPID\_CompactInterface\_Popup\_Graph into the new Pop-up screen.




3. Add a new HMI tag table called PID Controls.



4. Create the Water Temperature PID tag in the new table and map it to "dbWaterSystem".WaterTemperature.PID\_WaterTemperature.



- Fill in the interface of the popup with the newly created tag as well as static values.



6. Lastly, configure the Trend view with the tags you would like to trend.



Water Temperature PID Control

Auto Mode

Manual Mode

PID Auto

PID Manual

SP: 000.0 %

SP: 000.0 %

P: 000.0

PW: 000.0

Actual Input: 000.0 %

Actual Output: 000.0 %

EStop Value: 000.0 %

I: 000.0

DW: 000.0

D: 000.0

PreTune

Fine Tune

Manual Tune

Trend

Name	Style	Trend v...	Trend type	Source settings
<input checked="" type="checkbox"/> Water Temperature Actual		100	Cyclical real ti...	[dbWaterSystem_WaterTemperature_rPIDActualTemp]
<input checked="" type="checkbox"/> PID Output		100	Cyclical real ti...	[dbWaterSystem_WaterTemperature_rPIDOutput]
<a href="#">&lt;Add new&gt;</a>				

10:58:39 AM
10:58:59 AM
10:59:19 AM
10:59:39 AM

100%

fpPID\_CompactInterface\_Popup\_Graph\_1 [Screen module instance] [f...

Properties

Info

Diagnost

Properties

Interface

Animations

Events

Texts

Name

Static value

Dynamization

Properties\_Faceplate

HMI\_PIDInterface

sFormatPattern

sTitle

sUnit

Trend

999.9

Water Temperature PID Control

%

Water Temperature Actual, PID O...

Water Temperature PID